

ASUS RT-AC88U

Powered by
Asuswrt-Merlin

Logout

Reboot

English

Quick Internet Setup

General

Network Map

AiMesh

Guest Network

AiProtection

Parental Controls

Adaptive QoS

Traffic Analyzer

Game

Open NAT

USB Application

AiCloud 2.0

Tools

Advanced Settings

Wireless

LAN

WAN

Alexa & IFTTT

IPv6

VPN

Firewall

Administration

System Log

Network Tools

Operation Mode: wireless_router Firmware Version: 386.7 SSID: Traditions

VPN Status

VPN Director

VPN Server

VPN Client

TOR

Instant Guard

VPN Server - OpenVPN

PPTP

OpenVPN

IPSec VPN

The wireless router currently uses a private WAN IP address (192.168.x.x, 10.x.x.x or 172.16.x.x). Please refer to the [FAQ](#) and set up the port forwarding.

Basic Config

Server instance

Server 1

Enable OpenVPN Server

ON

VPN Details

Advanced Settings

Refer to the [System Log](#) for any error messages related to OpenVPN.

Before configuring the advanced settings of the OpenVPN server, ensure that these advanced settings options are compatible with the OpenVPN software in the client devices.

Advanced Settings

Interface Type

☒ TUN ☐ TAP

Protocol

☒ TCP ☐ UDP

Server Port

1194

(Default : 1194)

Authorization Mode

☒ TLS ☐ Static Key

Keys and Certificates

Edit...

Username/Password Authentication

☒ Yes ☐ No

Username / Password Auth. Only

☐ Yes ☒ No

TLS control channel security
(tls-auth / tls-crypt)

Disable

HMAC Authentication

Default

VPN Subnet / Netmask

10.133.0.0

255.255.255.0

Advertise DNS to clients

☐ Yes ☒ No

Data ciphers

CHACHA20-POLY1305:AES-128-GCM:AES-256-GCM:AES-12

Compression

Disable

Log verbosity

3

(Between 0 and 6. Default: 3)

Manage Client-Specific Options

☒ Yes ☐ No

Allow Client <-> Client

☒ Yes ☐ No

Allow only specified clients

☐ Yes ☒ No

Allowed Clients

Common Name(CN)	Subnet	Mask	Push	Add / Delete
			No	+

1 of 2

10/12/2022, 10:17 AM

TraditionsStPaulHouse	192.168.140.0	255.255.255.0	No	
TraditionsNaplesStore	192.168.135.0	255.255.255.0	No	
TraditionsNaplesHouse	192.168.150.0	255.255.255.0	No	

Custom Configuration

--username-as-common-name

Default

Apply

[Help & Support](#) [Manual](#) | [Product Registration](#) | [App](#) FAQ

2022 ASUSTeK Computer Inc. All rights reserved.